
HSC 10 – What's New 1/24 Matti Hietala, Matti Peltomäki, Fedor Vasilyev, Petri Kobylin, Antti Roine September 13, 2023

HSC 10 New Features



HSC 10 Releases

2023

HSC 10.4 September 2023 HSC 10.3 March 2023

2022

HSC 10.2 December 2022 HSC 10.1 March 2022

2021

HSC 10.0.8 December 2021 HSC 10.0.7 October 2021 HSC 10.0.6 June 2021 HSC 10.0.5 April 2021 HSC 10.0.4 January 2021

2020

HSC 10.0.3 November 2020 HSC 10.0.2 June 2020 HSC 10.0.1 March 2020 (including bug fixes only) HSC 10.0.0 January 2020

HSC 10 – What's New 2/24 Matti Hietala, Matti Peltomäki, Fedor Vasilyev, Petri Kobylin, Antti Roine September 13, 2023

New features 2023

New version of HSC 10 (ver. 10.4) has been released September 2023!

HSC Sim General:

- Flowsheet partial simulation of process areas is added.
- Dynamic reports calculate the statistics and study the assets utilization KPI of dynamic simulations.

HSC Sim Models:

- New High-Rate Thickener model is added.
- Reaction sheets using particles in several mineral processing units: Perfect Mixer, Conditioner, Bond Ball Mill, Pump Sump, Thickener (General), High-Rate Thickener and Water Tank. Convert particle's mineral into equivalent species and create reactions using particles. Reaction rates can be adjusted per particle's size.

HSC General:

- This is the last version supporting 32-bit application interfaces and 32-bit Microsoft Excel add-in.
- End User License Agreement (EULA) 1/2023 is updated.
- Installer is improved (For example, HSC add-in for Microsoft Excel is installed automatically).
- HSC Excel add-in example files (AddInSample.xlsx and AddInSample_EQ.xlsx) updated.
- Numerous small usability improvements and bugfixes.

New version of HSC 10 (ver. 10.3) has been released March 2023!

HSC Sim General:

- Speed improvements for dynamic simulation (Up to 2-3x faster simulation speed)
- Improved UI for Sim main window
 - o Function and tools logically grouped in menus and toolbars
 - Renaming of tools and panels
 - o New flowsheet tool called Visibility
 - o Improved flowsheet visualization
 - o Fixed Auto Route tool
 - Updated default options in static calculation
 - o Redesigned Names (Rename Alias) tool
- Stream Setup and mineral processing units contain full variable list. Add mass fraction, species concentration and pH for mineral flowsheet

HSC Sim Models:

- New screen, cyclone, crusher and HPGR models added
- Flocculant addition in generic thickener, improved cooling tower and filter

HSC General:

• Plenty of small usability improvements and bugfixes

New features 2022

New version of HSC 10 (ver. 10.2) has been released December 2022!

HSC Sim general:

- [Beta] New time series database to collect dynamic calculation data.
- [Beta] Dynamic mass balance report that utilizes the new time series database
- [Beta] Possibility to add dynamic calculation charts on the flowsheet
- Variable tree structure and new variables for minerals unit editor
- Improved speed with snapshot saving / loading
- Small improvements to the flotation cell model
- Stream Setup: Possibility to track which element is analyzed

HSC General:

- HSC Aqua: Possibility to estimate binary Pitzer coefficients for ions with two different AI routines: Elastic net model or Simoes equations
- HSC license agreement was updated as HSC Chemistry 10 EULA 1/2022. Delay of delivery time was added to the first paragraph of section **15. General**.

New version of HSC 10 (ver. 10.1) has been released March 2022!

HSC Sim general:

- Increased speed with various items (closing sim, saving flowsheet, etc.)
- Increased speed with process model fit and process optimizer with dynamic simulations
- Multiple fixes and smaller adjustments to the Name / Alias system in HSC Sim
- Usability improvements to ordering of variables/streams in stream tables and flow tables
- Scroll bars and search filters for units, streams, controls and cell references in the UI
- Manual for process model fit added
- + Multiple bug fixes and smaller improvements

Minerals

- Added ore blending to Bond Ball Mill
- Added support for global sieve series in Mass Balance
- Visualization added for different ores in the flowsheet
- New stream setup: Improved and simplified modal calculation dialog
- Possibility to describe particles flotation behavior with maximum recovery (Rmax, %) and flotation kinetic rate (k, min-1) in Conditioner unit and Kinetic Model Fit tool
- Hydro variable list additions: Sulfide sulfur, metal sulfates, sulfates, acid as "AcidName" flow and new measurement units for Total Dissolved Solids
- Hydro water phase equilibrium calculations utilizing Aqua routines are faster

HSC – OpenLCA

- HSC Sim OpenLCA: System supports dynamic calculations
- HSC Sim OpenLCA: Possibility to store environmental footprint calculation parameters for comparison

HSC General:

- HSC Aqua: Possibility to estimate binary Pitzer coefficients for ions with AI routine
- Updated Geo database (Added new mineral chemistries and new minerals, adjusted stoichiometric values)

New features 2021

New version of HSC 10 (ver. 10.0.8) has been released December 2021!

HSC Sim general:

- Scenario Editor (3D chart, running multiple scenarios improved)
- Templates for Unit tables for DLL units
- New Open LCA editor beta version
- Species converter minor improvements and manual update
- Mass balancing using size fractions
- New stream setup improvements (binary particle creation, using multiple sieve sets, UI improvements)
- Importing customs sheets into Reports
- New dynamic calculation controls (Dahlin, Feed forward, PID velocity form)
- New material cut-off model to separate materials according to particle property
- New blasting model for static blasting simulations
- General usability improvements, bug fixes and smaller improvements

HSC General:

• Updated Geo database

New version of HSC 10 (ver. 10.0.7) has been released October 2021!

HSC Sim general:

- Process Model Fit tool (Beta) published for all users
- First version of Unit Tables. User can present DLL unit variables in flowsheet in similar way as with the Stream Tables.
- First version of Partial Simulation. User can run only parts of the flowsheet when simulating. This option can be found in the Simulation Menu.
- New faster Mass Balance engine published for all users
- First version of new Species Converter DLL unit. UI update + now conversion species lists can be done mineral by mineral and gangue can be also defined.
- Improvements to Event Sheets (multiple true/false variables, bug fixes, moving of event columns etc.)
- Improvements to SET sheet stopwatch functionality
- Small speed improvements to Sim loading, course license checking, unit selector dialog loading, calculation, copy-paste and drawing
- Possibility to paste images and tables directly to flowsheet from clipboard
- Option to add user defined custom calculation sheets from units in the Reports tool
- Manuals added for new Species Converter
- + many bug fixes and smaller improvements

New version of HSC 10 (ver. 10.0.6) has been released June 2021!

HSC Sim general:

- New stream setup test version (beta). This includes many changes to the stream setup such as bigger UI changes, online modal calculations, support for ore properties / ore blending, improved water flow controls etc.
- Auto routing of streams is available in flowsheet drawing
- Dynamic unit variable lists are automatically merged
- New variables for dynamic unit
- Adaptive step size with automatic scaling for external controls
- Visualization and reporting for stream properties
- Possibility to get unit custom sheets to Reports

HSC Geo:

• Database update

New version of HSC 10 (ver. 10.0.5) has been released April 2021!

HSC Sim general:

- First implementation of stream property dialog with pressure drop variable
- Better integration of dynamic unit tank and input/output sheet variables
- Changed criteria for the recycle stream convergence (now it is less strict and it can be filtered)
- Attachments can be added for models in Model Base.
- Possibility to group runtime variables in DLL units
- Species list merge between hydro and dynamic unit. Species are now transferred automatically.
- Refactored OreMet Optimizer: Modified OPEX calculation method and added new parameters & tables
- New Magnetic Separation model based on Dobby and Finch model. Calculation is based on material magnetic susceptibility
- Logos and names (except unit icon logos) are changed according to the new brand
- PSD chart option added to the unit editor of minpro models
- PSD and other mineral processing charts added to the visualization mode as default panel, replacing the stream visualization setting panel
- Fixed an issue regarding slowness of the model when changing temperature in dynamic unit and inserting the flow into minpro unit.
- Custom species handling rework. This should fix the issue of custom species with bad data accidentally coming into the user database.
- Species converter is now more strict on the overall mass balance when used from the dynamic unit.
- Plenty of small usability improvements and bugfixes.

HSC Geo:

- Bugfixes and charts improvements
- Algorithm refactoring
- New import of 3DCT files
- Small usability improvements and bugfixes

New version of HSC 10 (ver. 10.0.4) has been released January 2021!

HSC Sim general:

- Option for automatic water vapor balance calculations in dynamic unit (Test version)
- Static model fitting with Model Optimization tool
- "% solids by volume" for minerals processing units. (Visualization, Reports, Stream Viewer)
- Fix for Species Converter operation in Dynamic Unit. Improved error minimization and now O will properly float if exact O measurement is OFF.
- Improved internal streams convergence check. Internal streams are now properly taken into account in mass and energy balance checking.
- Possibility to calculate individual runs in Scenario Editor (by right clicking on the row)
- Phase specific element flowrate for visualization in static hydro units
- Plenty of small usability improvements and bugfixes

HSC general:

- Update for Geo Database
- Small usability improvements and bugfixes

New features 2020

New version of HSC 10 (ver. 10.0.3) has been released November 2020!

HSC Sim general:

- Flowsheet opening, saving and simulation speed improved roughly 30%. Depending on the flowsheet, the increase can be up to 60%.
- Possibility to define initial guesses for circulation streams to speed up convergence
- New improved internal control method for the Newton-Raphson control
- Generic thickener unit extension (Enthalpy calculations, possibility to use as a CCD unit with adjustable washing efficiency)
- New Hydro variable list variables: Recovery, Thermal Energy, Heat Content
- Reaction enthalpy to hydro unit editor
- Reverse reaction calculations
- Equilibrium constant calculations for reactions
- Adjusted CP for DLL units
- Improved comminution models and model manuals
- Plenty of small usability improvements and bugfixes

HSC Sim new tools:

- Unit availability (visible in visualization and report)
- Residence time distribution tool
- Possibility to create test cases for continuous testing by using scenario editor

Geo general:

- Database extended
- Small usability improvements and bugfixes

New version of HSC 10 (ver. 10.0.2) has been released June 2020!

This release contains new features and bug fixes such as:

SIM

- HSC Sim model opening and saving speed improved 30%
- Easy way to combine different hydro models (automatic variable list merger)
- New Hydro variable list variables: Phase Transfer, Recovery percentage, Thermal Energy, Heat Content, Adjusted Density
- Improved comminution models
- Improvements in reports tool (filters and possibility to show alias and ID)
- Three new tutorial videos about dynamic simulations in YouTube: <u>https://www.youtube.com/watch?v=hC8utKwd9w0&list=PLc4W37RXMQWfeO4zBrwQZYN</u> <u>zXt2qU4UWa&index=13</u>
- Mass Balance tool calculation improvements (More stable)

NAV

- Better UI
- Faster and more accurate calculations
- New phase type: Solid solutions

GEO

- Database extended
- Importing mineralogical data in Inca/Aztec format added to Geo

OTHER MODULES

- Many small features and bugfixes

New version of HSC 10 (ver. 10.0.0) has been released January 2020!

The new release provides improvements and a number of new features. The new HSC 10 runs simultaneously with your previous HSC versions. A valid HSC 9 subscription entitles you to a free update to HSC 10.

Top new features

- New subscription based licensing replaces old perpetual licensing
- HSC 9 calculation module files are upward compatible with the new HSC 10
- Sim Model Base expands personal expertise to organization expertise
- Sim Model Optimization with Monte-Carlo, PSO, Simplex, MFit (SQP)
- Sim Model Convergence Monitor for static models
- Sim Dynamic Report is a new tool for collecting simulation data
- Sim file loading and calculation speed improvements
- Sim Unit Operation Protection
- Sim model combination improvements
- Sim OpenLCA dialog improved and updated
- Sim new generic unit operations
- Gem Equilibrium Module: Own Pitzer parameters, electrode potential calculations
- Aqua Module with own Pitzer database
- New Sampler Module with save/open features
- Diagram Navigator Module: new triangulation algorithm and several small improvements
- Data Processing Module with new algorithms and faster graphics
- Material Database Module with links to location maps
- HSC Main Database Module with new and updated data for chemical species
- HSC Main Menu with Sub Menu
- Many minor improvements and bug fixes

Model Base

- SharePoint database for HSC Sim process models. See Figure 1.
- Expands personal expertise to organization expertise.
- Routine that automatically creates SharePoint database.
- Default SharePoint folders: MinPro, Hydro, Pyro, Water, Energy, Plants, Users.
- Model Base stores process models, Process information, KPIs, and supplementary files.
- Search routine uses process info metadata (technology, products, etc.).
- End user must have a valid Microsoft license for the SharePoint site.

ctions											
	Es.	The second second			E.	- End	49	1000			
👱 🗄 C		- C		6	Ep		23		?		
ve Local Folder Sea	ch Add Folder	Add Personal	Rename	Delete	View Folder	View Files	Refresh	Ask Access	Help		
Copy View		Folder	Folder	Folder	Permissions						
Model View				Tools				Messages	Info		
HSC Models							Model Prope	rties KPIs			
Energy						1	Process	14.10			
Hydro							Process	s Name		Ettringite process	
🚞 Minpro							Techno			× Waste water treatment	
🚞 Plants								cnhology		× Precipitation	
🚞 Руго							Main Pr			× Ettringite × Gypsum	
🗁 Users							Plant T			× Water purification	
- 🗁 Water							Fidiliti	Abe		× water purilication	
→ → Ettringite proceed							Comme	nt		The process model was created for education purposes	
							RADRO	eport Number		53810.000	
								formation (URI)	The process does not represent OT technology	
							HSC Ve			9.9.3.20	
							Customer				
							Custom	her		Outotec research center	
							Site Na			ORC	
							Locatio			Pori	
							Countr			Finland	
							Coordir			61.4621;21.8683;11	
							Process D			and the d	
							Author			Fedor Vasilyev 4.12.2019 18.16	
								hanged s Version		4.12.2019 18.16	
							Review				
							Review			Antti Roine	
							Selecte			11.11.2019 15.00	
							Last mo	odified		4.12.2019 18.16	
							Last mo	dified by		Fedor Vasilyev	
del Name Ettringite proc											
ver URL /sites/HSCMod	Base/HSC Models	/Water/Ettringite	e process d	emo/Ettri	ngite process						

Figure 1. SharePoint database for process models is created automatically. Users can upload their models and supplementary files to the Model Base. The Model Base can be opened from the HSC main menu or accessed from HSC Sim. Model properties and key performance indicators can be viewed and edited in the Model Base.



HSC 10 – What's New 15/24 Matti Hietala, Matti Peltomäki, Fedor Vasilyev, Petri Kobylin, Antti Roine September 13, 2023

New KPI Dialog in Sim

- Summary of the process key performance indicators with links to the model. See Figure 2.
- Headings may be used with the Model Base keyword search routines.

ж с П с			ř		AB		-	-		AB	?	
Ê P	Mana and a state of the state o	Add Category Rem		ve Category Up Move Categ Down	ory Rename Category	Remove Move KPI KPI Row	Up Move KPI Down	Insert Sheet	Delete Sheet	Rename Sheet	Help	
Ed	it Cell Reference			Category		KPI			To	ols		
C 19	✓ SO4(-2a)	in treated water										
	В	С	D	E	F	G	н	Ĩ	J		К	
5	Category	KPI Name	Unit	Model Value	Desing Value	Warranty Value	Comment					
6	PROCESS CAPACITY			PM								
7		Feed water	t/h	1003.385	1100.000							
8		HAC feed	t/h	1.233								
9		Lime feed	t/h	1.116								
10		CO2 feed	t/h	0.341								
11		Ettringite product	t/h	8.160								
12		Gypsum product	t/h	15.424								
13		Calcite product	kg/h	0.396								
14		CaCO3/Calcite	%	69.087								
15		Ettringite	%	44.520								
16		CaSO4	%	98.504								
17		<name></name>		<insert cell="" reference=""></insert>								
18	KPI-WARRANTY											
19		SO4(-2a) in treated wate	r mg/L	48.066	250.000	250.000						
20		<name></name>	Ī	<insert cell="" reference=""></insert>								
21	KPI-OTHERS											
22		Electricity	kW	<insert cell="" reference=""></insert>			1					
23		Oil	t/h	<insert cell="" reference=""></insert>								
24		Steam	t/h	<insert cell="" reference=""></insert>								
25		<name></name>		<insert cell="" reference=""></insert>								
26	KPI-ENVIRONMENTAL											
27		Carbon		<insert cell="" reference=""></insert>								
28		SO2		<insert cell="" reference=""></insert>								
29		<name></name>		<insert cell="" reference=""></insert>								

Figure 2. Process information dialog contains a KPI sheet where the process key performance indicators can be summarized. The numerical data can be collected from the model using cell references which allows automatic updating of the values each time the model is changed.

Sim Model Optimization

- New tool for model optimization. See Figure 3.
- Direct optimization of any cell reference in Sim model.
- Four available algorithms: Monte-Carlo, PSO, Simplex, MFit (SQP).

ade	erl		Testal Solids Flows	(t/h) Solids Recovery (Rec-%)									
304]		Cu (wt-%)	Cu (Rec-%)									
									Number of cells	5			
								Conditionar	Rougher Patienten	200			
	Fred Hopper					_	ije or	Fistor Fee	Residence time i	mm 11.0		1653.1 85.7 0.1 14.8	
	T						and.	David	(veve)		Augrer 1	Ten 0.1 14.8	
	Crushing Plant	fael						276.0	14.3 Rouper Carc		[1804]		
	[cause]		nary Cruster					3.1	85.2 [usua] 138.0 3.1	7.2 42.6 Regime Cyc. OF			
		Prim Sc OS	1350.4 704	-					Rougher turp				54
	<u></u>	panel 1	0.5 70.						Saurint Faat Ragmong H	[/BLB]			
	del Optimization		Prim Provide			······			salou an		-	X 309.1 16.0	245.8
			-	-							-	2.8 87.0	0.1
	Run Multiple	More	8	🔶 🔰 🐴	👌 🔎 🗢	Combine Combine	with: <	h 🕪 💵	A 11 11		4	Caurar 1 Potation	Number of ce
lun	Reset Sheets +	Collapse *	Add Ad	d Delete Rename	Clone Nove Move	Sheets *	м	ve Move Group	CleanUp Empty Delete Selected Insert	Cel Set Normalization	Set Absolute	Hein Hein	and the second second second
			Optimization Custom		timization Left Right		L	R Right Columns	Columna Constrainta Referen		Value	Danal Danal	17215 Anudence ton
	Run Options	Visibility		Sheet					Data Columns	Normaliza		100 0100C	(ana)
270	~	Final					Charts					3 333 943	
	A	8	С	D	E	^	Iteration	Timerange					
3	Mode & N								Global Cost			Course 1 Surg	Cienter 2 Ficto
1	Mod		STATIC	Method	SIMPLEX		1					0274	A REALDER
17	Optimizatio		Our Black	Contract Contractions	Contraction in the	_	-16.0					(44)	
29	Unit Na Variable		Ore Block Ore feed	OreMet Optimizer Profit/time	OreMet Optimizer Control violation		-16.5 -						
11	Measurem		Ore leed	Proncy ume	control violation		-17.0 -						0.3 1.6 02 Card
32	Cell Refe		1885.66	17105.96	0.00	<inser< td=""><td>-17.5</td><td></td><td></td><td></td><td></td><td></td><td>7.3 83.1 [/#ve]</td></inser<>	-17.5						7.3 83.1 [/#ve]
33	SET / C		SET	GET	GET		1 1						
14	Optimiz	e SET	ON				-18.0						- Case
35	Objectiv			MAXIMIZE	MINIMIZE		-18.5 -					Care Ta Pe	
36	Objective Ca			END	END		-19.0	1				Danal	
37	Min Bo		100.00				-19.5					Fitale	
38	Max Bo Normalia		3000.00 826.00	880.00	0.10		-20.0					[rank	0.5
3	Rounds	OBJ	820.00	880.00	0.10		.50.0 .7	10 20	30 40 50	60 70	80	e3	
4	Round 0	-9.53	800.00	8554.31	0.02	_		10 20	Iteration	60 /0	- 00		
5	Round 1	-16.02	1461.95	14153.42	0.01				Global Position			and Tana Cana Fill	Pitration -
6	Round 2	-18.97	1824.98	16710.60	0.00			100000000	Giudai Postuon	CELECTOR	111111	Cort Filter Fault	2 inerere
7	Round 5	-19.24	1859.44	16935.54	0.00		2.3					- Ind	1
8	Round 9	-19.37	1881.54	17079.48	0.00		2.2 -						×
9	Round 12 Round 15	-19.37 -19.37	1881.68 1878.86	17080.42 17060.34	0.00								
50	Round 15 Round 18	-19.37	1878.86	17060.34 17060.57	0.00		52.1-					Caroler	-
52	Round 18 Round 25	-19.37	1878.90	17060.60	0.00		p					(and	
33	Round 26	-19.37	1878.91	17060.63	0.00		2.0 -					-	
4	Round 40	-19.40	1885.30	17103.66	0.00		ton						
5	Round 46	-19.40	1885.63	17105.79	0.00		21.9					30.3	1.6
6	Round 53	-19.40	1885.66	17105.96	0.00		1					27.4	88.1
57	Round 82	-19.40	1885.66	17105.96	0.00		1.8 -						
8	Round 89	-19.40	1885.66	17105.96	0.00		1						
59	Round 91	-19.40	1885.66	17105.96	0.00			10 20		60 70	80	en,	
70	Final	-19.40 feed optimiza	1885.66	17105.96	0.00	v			Iteration		Ore fee	ed	
				<		>							

Figure 3. The new Model Optimization tool allows optimizing of process performance.

HSC 10 – What's New 17/24 Matti Hietala, Matti Peltomäki, Fedor Vasilyev, Petri Kobylin, Antti Roine September 13, 2023

Sim Model Convergence Monitor

- New tool to finalize steady state calculations when convergence criteria are met. See **Figure 4**.
- Works for static models.
- Variables: Mass, heat, or both.
- An option is available to check the controls before completing the calculations.




Figure 4. The convergence monitor can be used to complete a steady state calculation once the convergence criteria are met. The convergence monitor can check the global mass or heat balance, or both at the same time. The numerical value of the convergence criterion is shown in the Log Viewer. The convergence monitor can also check that all the controls are set at their setpoints before completing the calculations.

HSC 10 – What's New 18/24 Matti Hietala, Matti Peltomäki, Fedor Vasilyev, Petri Kobylin, Antti Roine September 13, 2023

Improvements in dynamic calculations in Sim module

- Dynamic Report is a new tool to collect simulation data. See Figure 5.
- New variables for dynamic units.
- New features and bug fixes for Pyro and Hydro.
- Stream pipe delays.




Figure 5. Dynamic Report collects the values of the user-defined variables from streams, tanks, and cell references during simulations and presents the minimum, maximum, average, and final values of the variables.

Sim Calculation Speed

- Model loading speed improved.
- Model calculation speed improvements.
- Multithreading (parallel computing) for dynamic models.
- Automatic calculation order of static process flowsheets improved.

Sim Unit Operation Protection

- Makes it possible to protect unit calculation and shows only Input and Output sheets. See **Figure 6**.
- Converts a unit operation to a black box.
- Password and HSC serial number based protection.



Figure 6. The Unit Protection tool makes it possible to protect a unit calculation. It converts a unit operation to a black box so that the user can see only Input and Output sheets. Password and HSC serial number based protection.

HSC 10 – What's New 20/24 Matti Hietala, Matti Peltomäki, Fedor Vasilyev, Petri Kobylin, Antti Roine September 13, 2023

Sim Model Combination Improvements

- Process models may be imported into an existing model one by one.

Sim Environmental Features

- OpenLCA dialog improved and updated.

Sim New Features

- New generic units: Stockpile, Ore Bin.
- Updated generic units: Multicomponent option (Ball, Rod and AG/SAG mills), cyclone, flotation, mill.
- New default Hydro variables.
- New Diagnostics tool, which collects a warning log of possible problems for the end user.

Gem Equilibrium Module

- Own Pitzer parameters can now be used for aqueous solutions calculations in Gem.
- Electrode potential (E) calculations and plotting E for aqueous systems.

Aqua Module

- New database of user's own Pitzer parameters.
- Makes it possible to use own Pitzer data in Aqua calculations. See Figure 7.

Aqua																			-	. 🗆 🗙
3	🔏 Cut 📲	Paste			8	-			1	f(x)	🕢 Help									
File	Copy Ø	Find/Replac	Calculate	Aqua metho	-04-		-		n Database D	ensity	About									
•	-			•	•			Sets	Ca	lculator										
Main		dit		Calculatio	on Options		Pi	tzer Database		Tools	Info									
AB	~	Fe(+2a)																		
	А	В	С	D	E	F	G	н	1	J	K	L	M	N	0	Р	Q	R	S	т ^
1	Water Phase Data	Temp.	Amount	Amount	Amount	H Ideal	H Estimate	Cp Ideal	Cp Estimate	H Idea	I H Estim	ate Cp Idea	l Cp Estimate	e Osmotic	H2O Vapour Press.	r Sol. Vapour Press.	r Ionic Strength	рН	Relat. Humidity	FP
3		°C	kmol	mol-%	g	kcal/mol	kcal/mol	cal/(mol*K)	cal/(mol*K)	kcal/k	g kcal/k	g kcal/(kg	K) kcal/(kg*K)	Coeff.	Pa	Pa	mol/kg		%	°C
	Water Phase	75	57.50	100.00	1.15E+06		-69.20	16.44	17.68	-3458.3			0.88	0.45	38538.80	37916.07	4.00	0.00	98.38	-1.94
	Vater Species		Amount	Amount	Amount		H Estimate		Cp Estimate	AC	AC	Molalit		Elements						
6	Data	°C	kmol	mol-%	g	kcal/mol		cal/(mol*K)		Molar S				Fe	н	0	5	e-		
7 H	20 2(+2a)	75	5.55E+01 1.00E+00	96.52	1.00E+06 5.58E+04		-67.43	-6.37	17.78 36.84	1.02	1.02	5.55E+0 1.00E+0		1.00	2.00	1.00		-2.00		
	2(+2a) 04(-2a)	75	1.00E+00	1.74	9.61E+04		-217.48	-50.12	-6.90	0.04	0.04	1.00E+0		1.00		4.00	1.00	2.00		
10	54(-28)		OwnDB	1.74	5.012.004	-220.00	-217.40	-30.122	-0.50	0.04	0.04	1.00210	50.00	1		4.00	1.00	2.00	o x	
11		12	Table Delet																	
12			Table Delet	A		В	С	D	E	E	G	н	1 1	к	T I	M N	0	1	P ^	
13			. Ditto		Cation		teractions		6		0	n	,	ĸ	L.	1941 - 194 194	0		<u>.</u>	
14						Pitzer parar														
15			2		indence of	ritzer parai	neters													
16			4 a+	$\frac{b}{c} + c \cdot ln($	T) + dT -	$+ eT^2 + f^2$	T^{-2}													
18			5	r -		,													_	
19			6									validity rang				b(0)				
20				Cation (+)		Anion (-1	Show T	Min T [C] Ma			ax M Mi		a	b	c d	P		f	
21			7	53676			•	parameters		[r			/kg] [mol/kg]		-					
22			9	Fe(+2a)		SO4(-2a	a) [1	<u> </u>	0	100	4	0.1		5.19343	-508.2609	-0.01	609 1.83E	-05		
23			10																	
24			11																	
25			12																	
26			13																	
28			14																~	~
H 4 1	H Water Ph	ase/	4 4 > H	Binary param	eters / Theta	a parameters	Psi parameter	s/Lambda para	ameters/				<						>	>
Ou	totec																			

Figure 7. It is now possible to add your own Pitzer parameters in the Aqua module. These Own Pitzer parameters can also be used in the Gem and Sim modules.

Sampler Module

- New Sampler module replaces the old HSC 7 Sampler. See Figure 8.
- Better user interface and charts.
- Calculation results with comments can now be saved.




Figure 8. The new Sampler module replaces the old HSC 7 Sampler. The new Sampler features a better user interface and charts and allows the user to save the calculation results with comments.

HSC 10 – What's New 22/24 Matti Hietala, Matti Peltomäki, Fedor Vasilyev, Petri Kobylin, Antti Roine September 13, 2023

Improved Diagram Navigator Module

- New triangulation algorithm for diagram digitalization. See Figure 9.
- New crystallization path calculation is available for ternary phase diagrams in the HSC Navigator module and as an Add-in function.
- New visualization features.
- Improved user interface.




Figure 9. The new triangulation algorithm for the digitalization of the diagram surface allows the capturing of every tiny detail and use of the diagram for accurate calculation of crystallization paths. The digitized diagram surface and the crystallization path are visualized in a 3D chart. The crystallization path calculation is also available as an Excel Add-in function and can be used in other HSC modules.

HSC 10 – What's New 23/24 Matti Hietala, Matti Peltomäki, Fedor Vasilyev, Petri Kobylin, Antti Roine September 13, 2023

HSC Data Processing Module

- New algorithms: principal component analysis (PCA) (see Figure 10) and k-means clustering (See Figure 11).
- Faster graphics.




Figure 10. Principal component analysis (PCA) is a statistical procedure that uses an orthogonal transformation to convert a set of observations of possibly correlated variables into a set of values of linearly uncorrelated variables called principal components.

	Save Open	Add New Chart	Data Ar	alytics Auto U	Sec	Ab Modify Chart	Clone Chart	Show Hide Claculate Rov		et to Dar Layout Li	hboard ayout		About				
	Fie			Correlation Matrix				-		View	_	He			1		
3,	ita Table						*	Data J	Analytics - 1	197	Data Ana	lytics - 2	Dat	a Analytics - 3	Data Analy	ytics - 4	
1	£ 1.751971	3145657		k Means Clustering					Parel In All		i e	later.	n 19.992	- 1 e	Saleciae 40.003	- 1	entes NURSI
	A Name id	B mois	\$	Principal Component	Analysis	F	G sodium ci *					· Le. Kit	, verse		No.	*1.	-
	Unit					-					1	State		11 N	the the		tate II
	Min	14,003.000	25.000	6.980	4.380	1.170	0.250										Column II=
	Max	34,045.000	57.220	28.480	47.200	5.430	1.790						LAND.			: .	ni fani
	Average	20,841.040	40.903	13.374	20.230	2.633	0.669	311	- B B	at tell	1			-			(1) parts
	SD	6,962.917	9.553	6.434	8.976	1.270	0.370		11111	11111	1						
	Skew	0.534	-0.041	0.866	1.562	0.679	1.819				1 .	200	(au #4.)	-	1.000 miles (0.000)	-	
	Median	24,020.500	43.300	10.440	17.135	2.225	0.490	1		2	3				200	-	Six.
_	IQR	10,016.500	18.213	11.963 22.29	6.665	2.143	0.253			100					· 6		F. Mary
	1 2	14003 14004	47.17 49.16	22.29	17.49	4.08	0.74									1 ·····	Nerti .
	2	14004	49.10	21.28	41.65	4.82	1.64			12 TEL					1 . A. B.		1997
	4	14005	52.68	14.38	25.72	3.26	0.93		1.970	· .				1 2 6	10 M	-	
	5	14007	33.05	7.34	15.78	1.34	0.42				1 1 1			ų			
	6	14009	35.55	7.32	16.4	1.76	0.36		Sealer 344 #3 (#3		111		n 10100		Toparties #111		anna 101701
	7	14010	28.68	8.3	16.07	1.41	0.45		¥4								1.50
	8	14013	48.03	21.96	20.88	4.02	0.7			S.	-	1 34					
	9	14014	48.15	27.98	18.69	3.58	0.48	See.				1	The Br			- 1 A	(Diff)
	10	14015	49.57	13.7	29.07	3.62	1.1	141 141	17.4	7 1	1	1	. des			1	10 H
	11	14016	30.55	20.15	43.13	4.79	1.61	-	th:		3 6	A					1. 1. 1. 1.
	12	14017	28.29	8.05	16.72	1.31	0.43	1	24		1	·.					17.5
	13	14018	29.78	8.2	14.51	1.5	0.5	11111			1 2 2 2 2			1111	1111111111	7	
	14	14019	53.84	10.22	13.05	2.07	0.48	-	Salecia 42.013		+	(MARC)	n 15002	-	lasterias 40.003	1	Nandan Kiri
	15	14022	48.69	28.48	17.37	3.53	0.43										
	16	14023	47.53	21.11	21.54	4.02	0.7		1.10	6	: .	S	27 x.	1.	1 10 4		
	17	14024	48.53	13.14	30.38	3.55	0.99		1	155 :::		1 3	120	a i	The states a	n= 1	
	18	14025	28.35	19.99	45.78	5.08	1.63	1.1	14.	· * #		Sin	S. 200.00		Contraction of the second	n= :	All Berry
	19	14026 14028	28.13	8.34	16.19 4.96	1.42	0.45			7		2 3	•		2.5		
	20	14028	40.72	8.34 8.36	4.96	1.42	0.43	-			1			-		J ann ma	
	21	14029	49.73	25.65	4.39	2.51	0.48								0. 0. 0. 0. 0. 0.	111111	111111111

Figure 11. k-means clustering aims to partition n observations into k clusters in which each observation belongs to the cluster with the nearest mean, serving as a prototype of the cluster. The k-means clustering method implemented in HSC Data processing module clusters your data and visualizes the clusters in a multidimensional space.

Material Database Module

- New links to geographical location and maps.

HSC Main Database Module

- New and updated data for chemical species.

HSC Main Menu with Sub Menu

- The new Sub Menu lets the user easily hide rarely used module tiles. See Figure 12.




Figure 12. Rarely used module tiles can be easily moved into Sub Menu.

Others

- New Ptrack module (BETA version) for particle based balancing with mineral liberation data.
- Lots of small improvements and bug fixes.

HSC 10 Installation

- Default installation path C:\Program Files (x86)\HSC10.
- HSC 7, HSC 9, and HSC 10 can work simultaneously on the same computer.

New EULA Licensing Model with Subscription

- HSC 9 calculation module files are upward compatible with the new HSC 10.
- With the new subscription licensing model end users will get new software versions as they are released.
- The new licensing model does not support perpetual licenses without subscription. HSC 10 stops working after subscription period ends.
- Subscriptions are available for a period of one year or three years.